

## Text to Speech Converter – Readme

### Bot Overview

This bot performs the following:

This Metabot would render speech for a given text

### Prerequisites

- Automation Anywhere Enterprise v11.x

### Installation

- Download the bot from Bot Store.
- Double click on the .msi file.
- On Welcome to Installation wizard, click Next to continue.
- Click I agree to the terms in the license agreement radio button to accept the agreement.
- Get/Copy the License key from Bot Store Downloads into License Key, click Next to continue.
- Click Install to begin the installation.
- Click Finish to complete the installation.
- To view the installation, go to 'My Tasks' folder on AAE Client to see bot files.

### Uninstall

- Open Add/Remove Programs -> Select the Bot/Digital Worker to be installed
- Click uninstall

**Creates the following folder structure of the content in the AA Dir:**

- <AA Directory>
  - My Tasks
    - Bot Store
      - Read Content-AA (Folder)
        - My Tasks
          - [Read from File] Stub.atmx
        - Error Folder
          - Logs (Folder)
            - Error Logs Month-Day-Year.txt
          - Snapshots (Folder)
            - Error Snap Month-Day-Year.png
    - My Metabots
      - WordMetabot.mbot

## How to Use the Bot:

Use the following information to configure your bot:

| Parameter Name  | Type   | Direction | Additional Info                                                                                                                                                 |
|-----------------|--------|-----------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| vFilePath       | String | Input     | Provide file path.<br>E.g. C:\User\Desktop\TestBot.txt                                                                                                          |
| vResponse       | String | Output    | Returns a string containing all the content from a file                                                                                                         |
| vErrorFolder    | String | Input     | This is error folder inside bot folder which contains Logs and Snapshots folder (Already defined, no need to add value unless want to change location of file). |
| vLogFolder      | String | Input     | This folder contains Log file in case of error (Already defined, no need to add value unless want to change location of file).                                  |
| vSnapshotFolder | String | Input     | This folder contains Screenshot in case of error (Already defined, no need to add value unless want to change location of file).                                |

## Error Handling

- Each Bot folder contains the below hierarchy.
  - o Error Folder
    - Logs
      - Error Logs Month-Day-Year.txt: In case of any error, this file logs error message along with time stamp
    - Snapshots
      - Error Snap Month-Day-Year.png: In case of any error, this file captures screenshot of error.
- Task Status of bot is set to failed in case of errors.