

## Extract XPath from XML – Readme

### Bot Overview

This bot performs the following:

- The BOT will read through the hierarchy of the XML and generate the XPath for given elements.
- The Metabot gets the file path and the Xml root node and extracts the Xpath for the all the nodes within the root nodes.

### Prerequisites

- Automation Anywhere Enterprise v11.3.3

### Installation

- Download the bot from Bot Store.
- Double click on the .msi file.
- On Welcome to Installation wizard, click Next to continue.
- Click I agree to the terms in the license agreement radio button to accept the agreement.
- Get/Copy the License key from Bot Store Downloads into License Key, click Next to continue.
- Click Install to begin the installation.
- Click Finish to complete the installation. • To view the installation, go to 'My Tasks' folder on AAE Client to see bot files.

### Uninstall

- Open Add/Remove Programs -> Select the Bot/Digital Worker to be installed
- Click uninstall

**Creates the following folder structure of the content in the AA Dir:**

<AA Directory>

o My Tasks

▪ Bot Store

- XtractXPathfromXML-CitiusTech (Folder)

- My Tasks
  - Main\_XtractXPathfromXML.atmx
- Error Folder
  - ✦ Logs (Folder)
  - ✦ Error Logs Month-Day-Year.txt
  - ✦ Snapshots (Folder)
  - ✦ Error Snap Month-Day-Year.png
- My Metabots
  - ✦ ExtractXPathMetaot.mbot
- My Scripts

### How to Use the Bot:

Use the following information to configure your bot:

Parameter Name	Type	Direction	Additional Info
<b>vFilePath</b>	String	Input	The path of the input XML file
<b>vNodeName</b>	String	Input	Node value for which XPath to be returned

### Error Handling

- Each Bot folder contains the below hierarchy.
- Error Folder
  - Logs
    - Error Logs Month-Day-Year.txt: In case of any error, this file logs error message Along with time stamp
  - Snapshots
    - Error Snap Month-Day-Year.png: In case of any error, this file captures screenshot of error.
- Task Status of bot is set to failed in case of errors.

