



## **Bing Translate Bot**

### **Readme**

---

**Version 1.0**

**12/06/2019**

# Table of Contents

|   |                                     |
|---|-------------------------------------|
| <b>1. Introduction .....</b>                    | <b>3</b>                            |
| 1.1 Overview .....                              | 3                                   |
| 1.2 Common Use cases.....                       | <b>Error! Bookmark not defined.</b> |
| <b>2. Requirements &amp; Prerequisites.....</b> | <b>4</b>                            |
| 2.1 System Requirements.....                    | 4                                   |
| 2.2 Prerequisites .....                         | 4                                   |
| 2.3 Security Measures .....                     | 4                                   |
| 2.4 Disclaimers .....                           | 4                                   |
| <b>3. Getting Started .....</b>                 | <b>5</b>                            |
| 3.1 Skill Matrix .....                          | 5                                   |
| 3.2 Installation Hierarchy .....                | 5                                   |
| 3.3 Quick Start .....                           | 5                                   |
| 3.3.1 Setup .....                               | 6                                   |
| 3.3.2 Configuration .....                       | 6                                   |
| <b>4. Reports .....</b>                         | <b>Error! Bookmark not defined.</b> |
| <b>5. Logs .....</b>                            | <b>8</b>                            |
| <b>6. Troubleshooting &amp; Support .....</b>   | <b>9</b>                            |
| 6.1 Support .....                               | 9                                   |
| 6.2 FAQs.....                                   | 9                                   |
| <b>Appendix A: Record of Changes .....</b>      | <b>10</b>                           |
| <b>Appendix B: Acronyms.....</b>                | <b>11</b>                           |
| <b>Appendix C: References .....</b>             | <b>12</b>                           |

# 1. Introduction

---

This document contains all essential information for users to make full use of the Bing Translate Bot. This manual includes a description of the functions and capabilities as well as step-by-step procedures for the setup & configuration of the Bot.

## 1.1 Overview

The Bing Translate bot is meant to be used as a reusable utility component to enable language translation in 64 languages to be used in any number of custom bots that users create. It simply takes in the input of the text needed to be translated as well as the target translation language. The bot will then output the text translated to the target language.

**Example:**

**InputText:** 本文檔相當不錯。

**OutputLanguage:** English

**OutputText:** This document is pretty good.

## **2. Requirements & Prerequisites**

---

### **2.1 System Requirements**

Windows 64-bit and 32-bit versions are supported. No specific hardware requirements outside of those requirements needed for the installation of the Automation Anywhere enterprise client as well as Automation Anywhere 11.x and above.

### **2.2 Prerequisites**

The bot only uses Automation Anywhere enterprise/community client and Internet Explorer.

### **2.3 Security Measures**

No specific Security Measures required as this bot utilizes a publicly available website and


### **2.4 Disclaimers**

Bot is provided for use as-is, but can be altered/customized to meet your needs.

## 3. Getting Started

---

### 3.1 Skill Matrix



### 3.2 Installation Hierarchy

#### My Tasks\Bing Translate-Automation Anywhere\My Tasks

MasterBot.atmx – Main processing bot – just a dummy bot to show how to invoke the metabot.

#### My Tasks\Bing Translate-Automation Anywhere\Error Folder

##### Logs

ErrorLogs date.txt – records all bot errors with date/time

##### Snapshots

Recent screen captures on bot failures.

#### My MetaBots

BingTranslate.mbot – metabot for language translation processing.

### 3.3 Quick Start

The Bing Translate Bot should work out of the box. Just press play and see a message store in the MasterBot.atmx translated from Chinese to English.

### 3.3.1 Setup

Once the install is complete, launch the MasterBot.atmx. Here you will find the vInputText and vOutputLanguage variables with definitions. As the bot executes, an Internet Explorer window will open up, enter the input text, set the target language field, and

### 3.3.2 Configuration

| INPUT VARIABLES |      |           |  |               |
|-----------------|------|-----------|--|---------------|
| Variable Name   | Type | Mandatory | Purpose  | Example Input |
| vInputText      | Text | Yes       | Text to be translated in any of the 64 supported languages.          | 本文檔相當不錯。      |
| vOutputLanguage | Text | Yes       | Identifies the language you are trying to convert the Input Text to. | English       |

| OUTPUT VARIABLE |      |           |  |                                      |
|-----------------|------|-----------|--|--------------------------------------|
| Variable Name   | Type | Mandatory | Purpose  | Example Output                       |
| vOutputFileName | Text | Yes       | The resulting translated text returned from the Bing Translate Metabot | <i>This document is pretty good.</i> |

| Supported Input/Output Languages |                |                  |                 |
|----------------------------------|----------------|------------------|-----------------|
| Afrikaans                        | Filipino       | Korean           | Serbian (Latin) |
| Arabic                           | Finnish        | Latvian          | Slovak          |
| Bangla                           | French         | Lithuanian       | Slovenian       |
| Bosnian (Latin)                  | German         | Malagasy         | Spanish         |
| Bulgarian                        | Greek          | Malay (Latin)    | Swedish         |
| Cantonese (Traditional)          | Haitian Creole | Maltese          | Tahitian        |
| Catalan                          | Hebrew         | Maori            | Tamil           |
| Chinese Simplified               | Hindi          | Norwegian Bokmål | Telugu          |
| Chinese Traditional              | Hmong Daw      | Persian          | Thai            |

|          |            |                    |              |
|----------|------------|--------------------|--------------|
| Croatian | Hungarian  | Polish             | Tongan       |
| Czech    | Icelandic  | Portuguese         | Turkish      |
| Danish   | Indonesian | Querétaro Otomi    | Ukrainian    |
| Dutch    | Italian    | Romanian           | Urdu         |
| English  | Japanese   | Russian            | Vietnamese   |
| Estonian | Kiswahili  | Samoan             | Welsh        |
| Fijian   | Klingon    | Serbian (Cyrillic) | Yucatec Maya |

## 4. Logs

---

Logs are generated from the MasterBot.atmx and stored in the My Tasks\Bot Store\Bing Translate-Automation Anywhere>Error Folder\Logs directory.

The BingTranslate.mbot does not create any logs of its own.



## **5. Troubleshooting & Support**

---

### **5.1 Support**

Should you need support for the BingTranslate MetaBot or MasterBot.atmx, please post a note to the community at <http://apeople.automationanywhere.com>

### **5.2 FAQs**

## Appendix A: Record of Changes

| No. | Version Number | Date of Change | Author      | Notes   |
|-----|----------------|----------------|-------------|---|
| 1   | 1.0            | 12/6/2019      | Micah Smith | Initial bot release. This bot is primarily released in support of the Automation Anywhere Labs/tutorials. |

## Appendix B: Acronyms

| No. | Acronym | Description |
|-----|---------|-------------|
|     |         |             |

## Appendix C: References

| No. | Topic   | Reference Link             |
|-----|---|----------------------------|
| 1   | How to Create a Credential in Credential Vault? | Click <a href="#">here</a> |
|     |   |                            |