



Currency Converter using Python

Readme

Version 1.0

04/05/2023



Table of Contents

1. Introduction.....	3
1.1 Overview.....	3
1.2 Use Cases	3
2. Requirements & Prerequisites.....	4
2.1 System Requirements.....	4
2.2 Prerequisites.....	4
3. Getting Started	5
3.1 Quick Start	5
3.1.1 Setup	Error! Bookmark not defined.
3.1.2 Configuration	5
4. Support & FAQs	7
4.1 Support	7
4.2 FAQs.....	7
Appendix A: Record of Changes	8
Appendix B: References.....	9



1. Introduction

This document contains all the essential information for the user to make full use of this A360 Bot. It includes a description of the functions and capabilities and step-by-step procedures for the setup & configuration of the Bot.


1.1 Overview

This sub bot converts currency using python script. The Bot takes two variables (from and to) as input from user and runs them as argument in function of Python script, which gives converter value.

This Bot includes conversion of “USD JPY BGN CYP CZK DKK EEK GBP HUF LTL LVL MTL PLN ROL RON SEK SIT SKK CHF ISK NOK HRK RUB TRL TRY AUD BRL CAD CNY HKD IDR ILS INR KRW MXN MYR NZD PHP SGD THB ZAR” currencies.

Note: The currency should mention in form of Currency code (e.g.- INR for Indian Rupees)

1.2 Use cases





2. Requirements & Prerequisites

2.1 System Requirements

[Enterprise A2019 \(Cloud deployed\) and Community Edition device requirements.](#)

Review the machine hardware specifications, operating system versions, and browser types supported by Automation Anywhere Enterprise for creating and running bots and command packages as an Enterprise A2019 (Cloud deployed) or Community Edition user on your local machine.

2.2 Prerequisites

1. *User should have a A2019 installed to take a benefit of this automation.*
2. User should be use a Python Script – 2.10.0 Package.
3. User should be download python -3.10.7
4. User should currency mentions in form of Currency code (e.g.- INR for Indian Rupees).



3. Getting Started

3.1 Quick Start

3.1.1 Configuration and Use

1. Download the Bot from the Bot-store.
2. Check the downloaded bot in your local machine private/Public section.
3. Once Bot is downloaded you are good to go for a run.
4. Convert Currency one currency code to another currency code.

○ **For Configuring the Bot –**

INPUT VARIABLES: Input Variables to be mentioned in this Table				
Variable Name	Type	Mandatory	Purpose	Example Input
iStrFromType	String	Mandatory	Currency type	USD
iStrToType	String	Mandatory	Currency type to be converted in	INR
iStrProjectFolder	String	Mandatory	ProjectFolder path to save the logs	D:\ ProjectFolder

OUTPUT VARIABLES: Output Variables to be mentioned in this Table.			
Variable Name	Type	Mandatory	Purpose
oStrErrorMessage	String	Mandatory	For Error Message
oNumErrorLineNumber	Number	Mandatory	For Error Line Number
oBoolFlgErrorStatus	Boolean	Mandatory	For error status



oStrPythonFunctionOutput	String	Mandatory	Python Script Return Value Parameter
--------------------------	--------	-----------	--------------------------------------



4. Support & FAQs

4.1 Support

Free bots are not officially supported. You can get access to Community Support through the following channels:

- You can get access to Community Support, connecting with other Automation Anywhere customers and developers on [APeople – the Bot Building Forum](#), the [Bot Store Support Forum](#), or the [Developers Everywhere Group](#).
- Automation Anywhere also provides a [Product Documentation portal](#) which can be accessed for more information about our products and guidance on [Enterprise A2019](#).

4.2 FAQs

For questions relating to Enterprise A2019: See the [Enterprise A2019 FAQs](#).



Appendix A: Record of Changes

No.	Version Number	Date of Change	Author	Notes
1	1.0	04-May-2023	Predikly Technologies Pvt Ltd.	N/A



Appendix B: References

No.	Topic	Reference Link
1	Overview of Enterprise A2019	Click here
2	Guidance: Building basic A2019 bots	Click here
3	Guidance: Building A2019 action packages	Click here
4	APeople Community Forum	Click here
5	Automation Anywhere University	Click here