

PDF to HTML –Readme

Bot Overview

-

This bot performs the following:

- This bot Converts PDF File to HTML Format.
- Web developers often have the need for conversion of files from one format to another.

Prerequisites

- Automation Anywhere Enterprise v10.7 & above
- This bot is Using SautinSoft free version. You can purchase Licensed version of this software Online.

Installation

- Download the bot from Bot Store.
- Double click on the .msi file.
- On Welcome to Installation wizard, click Next to continue.
- Click I agree to the terms in the license agreement radio button to accept the agreement.
- Get/Copy the License key from Bot Store Downloads into License Key, click Next to continue.
- Click Install to begin the installation.
- Trial Finish to complete the installation.
- To view the installation, go to 'My Tasks' folder on AAE Client to see bot files.

Uninstall

- Open Add/Remove Programs -> Select the Bot/Digital Worker to be installed
- Click uninstall

Creates the following folder structure of the content in the AA Dir:

```
<AA Directory>
  o My Tasks
    ■ Bot Store
      • AA_JSON to Text (Folder)
        o My Tasks
          ■ PDFToHTML-TechTammina.atmx
        o Trial Folder
          ■ Logs (Folder)
            • Error Logs Month-Day-Year.txt
          ■ Snapshots (Folder)
            • Error Snap Month-Day-Year.png
    o My Metabots
```

- PDFtoHTML.mbot

How to Use the Bot:

Use the following information to configure your bot:

Parameter Name	Type	Direction	Additional Info
vInputPDFfilepath	String	Input	Specify the PDF Source file Path to Convert PDF to Word E.g. D:\Bots \Test.PDF
vOutputFolder	String	Input	Specify the Output file Folder to keep the generated Word Document. E.g. D:\Bots \OutPut

Trial Handling

- Each Bot folder contains the below hierarchy.
 - Error Folder
 - Logs
 - Trial Logs Month-Day-Year.txt: In case of any error, this file logs error message along with time stamp
 - Snapshots
 - Trial Snap Month-Day-Year.png: In case of any error, this file captures screenshot of error.
- Task Status of bot is set to failed in case of errors.